



FarmLab


3 D P R I N T E R M A N A G E R

Quick Guide

FIRST RECOMMENDATIONS



Never shut down the raspberries by **disconnecting** the power supply unit without shutting down the system first! This will result in data corruption and malfunction of the SD-Card.



Always shut down the system from OctoPrint first and then disconnect the power supply unit once the server is no longer available.

FIRST RECOMMENDATIONS


```
login as: pi  
pi@172.22.95.240's password:  pi@octopi:~ $ sudo shutdown now
```

Alternatively, you can SSH into the system of the Raspberry Pi with PuTTY and write the following command:

- `sudo shutdown now`


Never shut down the raspberries by **disconnecting** the power supply unit!

STRUCTURE OF FARMLAB




POSTGRESQL-SERVER

. Information about the Spools (Type of material, remaining material, printer, etc.) is saved in the PostgreSQL database.



GETTING STARTED

Add your printers to the system



FarmLab reads credentials from 3 different configuration files:

- **postgresConfig** has the credentials to connect the system to the PostgreSQL database.
- **printerConfig** has the credentials to connect to each OctoPrint instance
- **TSDConfig** has the credentials to connect to the “The Spaghetti Detective” server

To add new printers to the system, **only the printerConfig file** should be changed.

GETTING STARTED

Add your printers to the system

printerConfig-file

	A	B	C	D
1	NAME	IP	API-KEY	POSTGRES-ID
2	Alpha	http://172.22.95.240	5B6B62963F054A20AFBFECF15E3CE1D0	13418398-dda6-11eb-a4ef-e45f01155c5f
3	Bravo	http://172.22.95.241	CF52343D331148BD927B5DD5A0FC5C14	2e2f1904-dda6-11eb-bbe2-e45f01155c43
4	Charlie	http://172.22.95.242	C9480239A77E48B896B3CE15B6623714	2b306d84-dda6-11eb-8831-e45f01155af4
5	Delta	http://172.22.95.243	3C745D0104B14534A57B047AF2858354	46982206-dda6-11eb-a0ee-e45f01155e2a
6				

In order to connect a printer to the system, FarmLab needs the **IP-address** of the raspberry pi where OctoPrint is running, an **Application Key** and a **Postgres-ID**. The name in the file can be changed freely. FarmLab reads these credentials from the **printerConfig file**.

Application Key

APPLICATION KEY

OctoPrint Settings

Terminal Filters

GCODE Scripts

FEATURES

Features

Webcam & Timelapse

Access Control

GCode Viewer

API

Application Keys

OCTOPRINT

Server

Folders

Appearance

☐ Alpha

Dashboard 2

API Key: 5B6B62963F054A

☐ Alpha

Prusa Slicer

API Key: 6CB6467D512D

«

1

»

Manually generate an application key

User

Alpha

Application identifier

Dashboard

Generate

About OctoPrint




System info

Close

Save

Generate an **Application Key** for each instance you want to connect with FarmLab and copy it in the printerConfig file.

Postgres-ID



In order to know the **Postgres-ID** of a printer we make the following:

- Make sure OctoPrint is connected to the external PostgreSQL data base (1 and 2).
- Then go back to the main page and select a spool that is **not being used by another printer** and remember its name (3).

POSTGRES-ID

Add your printers to the system

```
Server [localhost]: 172.22.95.249
Database [postgres]: octoprint_filamentmanager
Port [5432]: 5432
Username [postgres]: octoprint
Password for user octoprint:
```

4

tool	client_id	name	material	weight	used
0	2b306d84-dda6-11eb-8831-e45f01155af4	VIRT. SPOOL YELLOW	PETG	1000	15.2483
1	46982206-dda6-11eb-a0ee-e45f01155e2a	VIRT. SPOOL GREEN	PLA	1000	0
3	46982206-dda6-11eb-a0ee-e45f01155e2a	VIRT. SPOOL RED	PLA	1000	0
0	2e2f1904-dda6-11eb-bbe2-e45f01155c43	VIRT. SPOOL BLUE	PLA	1000	6.53997
1	2e2f1904-dda6-11eb-bbe2-e45f01155c43	VIRT. SPOOL GREEN	PLA	1000	0
2	2e2f1904-dda6-11eb-bbe2-e45f01155c43	VIRT. SPOOL PINK	PETG	1000	0
3	2e2f1904-dda6-11eb-bbe2-e45f01155c43	VIRT. SPOOL RED	PLA	1000	0
4	2e2f1904-dda6-11eb-bbe2-e45f01155c43	VIRT. SPOOL WHITE	PETG	1000	0
0	46982206-dda6-11eb-a0ee-e45f01155e2a	VIRT. SPOOL YELLOW	PETG	1000	15.2483
4	46982206-dda6-11eb-a0ee-e45f01155e2a	VIRT. SPOOL YELLOW	PETG	1000	15.2483
0	332c54f8-e571-11eb-8484-e45f01155cb0	VIRT. SPOOL RED	PLA	1000	0
2	46982206-dda6-11eb-a0ee-e45f01155e2a	VIRT. SPOOL YELLOW	PETG	1000	15.2483
2	13418398-dda6-11eb-a4ef-e45f01155c5f	VIRT. SPOOL MAGENTA	PETG	1000	0

(13 rows)

5

Open PSQL and connect to the server with your credentials (4), and type the following:


- `SELECT selections.tool, selections.client_id, spools.name, profiles.material, spools.weight, spools.used
FROM profiles JOIN spools ON profile_id=profiles.id JOIN selections ON spool_id=spools.id ORDER BY
client_id, tool;`

You will see a table that looks like number 5. Search for the printer that is using the spool you selected in step 3. The **client_id** is the number you have to **copy on the printerConfig file as POSTGRES-ID**.





2 of 2

FarmLab

CAMERAS CONTROL PANEL JOB HISTORY TSD SERVER



Disconnected: 3
Operational: 1
Printing: 0
Paused: 0

Alpha	Bravo	Charlie	Delta
			
0%	0%	0%	100%
Status: Disconnected	Status: Disconnected	Status: Disconnected	Status: Operational
Time Left: -	Time Left: -	Time Left: -	Time Left: 00h 00m
Job Name:	Job Name:	Job Name:	Job Name: IG_xyzCalibration_cube_0.3mm_1
<div>Stop</div> <div>Resume</div>	<div>Stop</div> <div>Resume</div>	<div>Stop</div> <div>Resume</div>	<div>Stop</div> <div>Resume</div>

If the credentials are right, you can now start FarmLab.


FarmLab consists of **4 different modules**:

1. Cameras
2. Control Panel
3. Job History
4. TSD-Server

FarmLab

Cameras

FARMLAB - CAMERAS



The screenshot displays the FarmLab 3D Printer Manager interface. At the top, there are tabs for CAMERAS, CONTROL PANEL, JOB HISTORY, and TSD SERVER. The main area shows four camera feeds labeled Alpha, Bravo, Charlie, and Delta. Each feed has a status bar below it. Alpha, Bravo, and Charlie are all 'Disconnected' with a 0% progress bar. Delta is 'Operational' with a 100% progress bar. Below each status bar are 'Stop' and 'Resume' buttons. A 'Time Left' field is also present for each printer. The job name for Delta is 'IG_xyzCalibration_cube_0.3mm_1'. In the top right corner, there is a summary box showing the overall status: Disconnected: 3, Operational: 1, Printing: 0, Paused: 0. The FarmLab logo is in the top left corner.

1


2

3

The **cameras module** presents a big picture of the stream of the **webcams** from octoprint. An **overview** of the printers (2) is also presented to the user. There the user can see how many printers have a specific status. Also, **basic controls** (3) are available.

FarmLab

Control Panel




The control panel offers 5 different types of controls:

1. Printer controls to pause, resume and cancel the print job. Also, a connection between the printer and OctoPrint can be established by pressing the “connect” button.
2. File management controls. From here G-Code can be uploaded or deleted for each OctoPrint instance. Also, you can select and print a file stored in OctoPrint.
3. With the printhead controls the user can move the Z-axis of the printer.
4. Filament manager controls to change the spools being used by the printer.
5. A button that open the server of OctoPrint in a web browser.

Furthermore, the main state variables are presented to the user, like temperature, remaining time, status, etc.

FARMLAB – UPLOAD G-CODE AND START A PRINT JOB

CAMERAS CONTROL PANEL JOB HISTORY TSD SERVER



Alpha Open OctoPrint Bed 0°C / 0°C Tool 0°C / 0°C tool0 - VIRT. SPOOL MAGENTA - PETG - 1000 [g]

Status: Disconnected

Job Name:

0%

Connect Pause Resume Cancel Update Print

CAMERAS CONTROL PANEL JOB HISTORY TSD SERVER



Alpha Open OctoPrint Bed 21°C / 0°C Tool 21°C / 0°C tool0 - VIRT. SPOOL MAGENTA - PETG - 1000 [g]

Status: Operational

Job Name:


0%

Connect Pause Resume Cancel Update Print

- Start the process by establishing a connection between OctoPrint and the printer by clicking the “Connect”-button. Sometimes this process can take several seconds.

FARMLAB – UPLOAD G-CODE AND START A PRINT JOB

CAMERAS CONTROL PANEL JOB HISTORY TSD SERVER



SELECT THE G-CODE YOU WANT TO UPLOAD

File Path:

C:/Users/Ivan/Desktop/Pawn_0.3mm_PLA_MK3MMU2_58m.gcode

Browse

Upload




Pawn_0.3mm_PLA_MK3MMU2_58m.gcode was successfully uploaded.
Please update the job search box

OK



- Once the printer is operational, click the upload button. A window to upload your G-Code is going to open. Search your desired G-Code with the “Browse” button and the upload it.

FARMLAB – UPLOAD G-CODE AND START A PRINT JOB





- Now press the “Update” button, then open the combo-box and select your desired file and press “Print”.

FARMLAB – CREATE SPOOLS AND CHANGE SPOOL IN USE




- In the OctoPrint Settings go to “Filament Manager” and create a new profile. Fill the dialog window and save the profile.

FARMLAB – CREATE SPOOLS AND CHANGE SPOOL IN USE





- Click “Add Spool” and fill the dialog window with the information of the new spool. Finally click “Save”.

FARMLAB – CREATE SPOOLS AND CHANGE SPOOL IN USE





OR




- If you want to change the spools being used by a printer, you can do so directly in OctoPrint (left) or in the dashboard of FarmLab (right) by clicking the button with the spool icon. For multi-material printers, you can select a spool for each tool the printer has.

CONNECT PRUSA-SLICER WITH FARMLAB



To send G-Code directly to each octoprint instance we have to connect PrusaSlicer with each OctoPrint instance. For this go to printer, then click “Add/Remove printers” and then “Add physical printer” (step 1). Then fill the dialog with the corresponding credentials (Step 2).

CONNECT PRUSA SLICER WITH FARMLAB



Now upload the STL-file you want to slice to the PrusaSlicer. Select the printer you want to send the G-Code to and then slice the model. Then press the “G” button in order to send the G-Code to the selected OctoPrint instance (Step 3).

Finally, go to the control panel of FarmLab, update the combo-box and search for the uploaded file (step 4).

FarmLab

Job History

FARMLAB – JOB HISTORY

CAMERAS

CONTROL PANEL

JOB HISTORY

TSD SERVER

All Printers

Import CSV

Alpha

Import CSV

Bravo

Import CSV


Charlie

Import CSV

Delta

Import CSV

FarmLab helps you retrieve **historical data from the printers** in the form of a CSV file. You can either download the **data for each printer individually** by clicking the button “Import CSV” under the name of a specific printer or download the **data for all the printers** by clicking the button under “All printers.”




Please log in

Delta

.....

☒ Remember me [Forgot password?](#)

Log in



Downloads



Location
C:\Users\ . [Change](#)

Ask where to save each file before downloading ☒

FarmLab downloads the CSV-files through your web browser. Therefore, you have to **click “Remember me”** when logging into OctoPrint on your web browser. Also, you have to enable the option to **“Ask where to save each file before downloading”** in your web browser. If something is not right, the browser will show the following message:





- {"error": "You don't have the permission to access the requested resource. It is either read-protected or not readable by the server."}

READ CSV-FILES



When downloading historical data via FarmLab, a new folder called **Job_History_date_time** will be created with a **CSV-File** for each printer.



READ CSV-FILES



In order to open the CSV-files of the printers, go to excel, then click “Data”, “Get Data”, “From File”, “From Folder” (**Step 1**). Select and open the folder where the CSV-files where stored. Next, click on “Combine & Transform Data” (**Step 2**) and in the next window click “OK”. After that, we have to prevent excel to change the type of the data in the cells by clicking the X in “Changed Type” (**Step 3**). Finally click “Close & Load” on the top left (**Step 4**).

FarmLab

The Spaghetti Detective Server



You can access the TSD-server directly from FarmLab or via your web browser by typing the **IP-address of the server and the port** e.g., 172.22.95.251:3334